

Software License Activation Code Certificate



These activation instructions can also be found at www.hp.com/go/ice-license.

This certificate entitles the owner to licenses for the following software product(s):

- HP Insight Control Environment
- HP Insight Server Migration software for ProLiant (SMP)
- VMware software

HP Insight Control Environment uses two license keys and one license file. For successful operation all three licenses must be applied to each managed target system.

License Key 1: The Insight Control Environment key contains hidden subkeys for HP Insight Power Manager software, HP Virtual Machine Management Pack, HP Performance Management Pack, and HP Vulnerability and Patch Management Pack.

If you are using Insight Control Environment 3.00, you must use the HP Insight Software 3.00 integrated installer to enable the suite licensing. Starting with version 3.00, the Insight Control Environment licensing is now done from the Deploy -> License Manager menu.

Note: The product will not be listed until you add the first key.

To add a key from HP Systems Insight Manager:

1. Go to **Deploy -> License Manager**.
2. Click **Add Licenses**.
3. Enter the key in the **Specify Key String** field. Click **Process**.
4. When the key details appear, click **Add Licenses Now**.

To apply a license to a system from Deploy -> License Manager:

1. Go to **Deploy -> License Manager**
2. Select **Insight Control Environment** in the Product License Information list, and then click **Manage Licenses**.
3. A list of license keys appears. Click **Apply Licenses**.
4. Select the systems to license, then click **Apply** and **Next**.
5. Select the unlicensed systems and then click **Select License**.
6. Select the license key to use and then click **Apply License**.

If you are using Insight Control Environment 2.30 or 2.35, you must use the HP Insight Control Management integrated installer to enable the suite licensing. The menus will not appear until at least one HP ProLiant BladeSystem or ML/DL server has been correctly discovered.

To add a key in HP Systems Insight Manager:

1. Go to the Deploy -> License Manager menu.
2. Click **Add Licenses**.
3. Enter the key in the **Specify Key String** field. Click **Process**.
4. When the key details appear, click **Add Licenses Now**.

To apply a license to a system:

1. Go to **Deploy -> Insight Control Licenses -> Insight Control Environment Keys (ML/DL)**
2. Select the systems to license, then click **Apply** and **Next**.
3. Select the unlicensed systems and then click **Select License**.
4. Select the license key to use and then click **Apply License**.

License Key 2: Your iLO Advanced license key activates iLO Advanced features. These instructions assume the network client has a network connection to the iLO or iLO 2 management processor.

To install the iLO Advanced license and enable the iLO Advanced functionality using a supported web browser:

1. Log in to iLO or iLO 2 with a user ID that has the Configure iLO Settings privilege.
2. Click the **Administration** tab and then click **Licensing**.
3. Enter the 5 x 5-character license key in the space provided.
4. Click **Install**. The End User License Agreement (EULA) confirmation displays. The EULA details are available with the license kit.
5. Click **OK** to accept the terms of the EULA enclosed with this product. The licensed features are now enabled.

License File: Your HP Insight Rapid Deployment software (RDP) license file may contain licensing for one or more nodes. One license is required for each managed target system. Load the license file into the Deployment Server using the License Utility to apply your license.

Shut down all Deployment Server Consoles and Deployment Server Web Consoles. Click **Start -> Programs -> Altiris -> Deployment Solution -> Product Licensing Utility**. Enter the path to the new license file in the **Activation Key File Information** field and then click **Next**.

Your HP Insight Server Migration software for ProLiant key contains five X2V migration licenses. One license is required per migration performed. Upon completion of the migration, a license is consumed.

To add license keys:

1. Open the HP Insight Server Migration for ProLiant application and click the **License** tab.
2. Enter the new license key in the Add Key section and click the **Add** button. Note that license keys are case sensitive.

The following resources are available on the web at www.hp.com/go/insightcontrol:

- Access to software downloads
- Installation and user guides
- Support and services information

To access your VMware software licenses, you must register the attached Partner Activation Codes (PAC) at www.vmware.com/code/hp.

At the Partner Activation Code Registration page you will be prompted to register the unique PAC(s).

NOTICE: If you lose this certificate, we are unable to issue a replacement. Safeguard this certificate and register your software and Software Technical Support immediately.

This certificate is your proof of product purchase. You must register and exchange each activation code for a license key to receive proper subscription service. Multiple activation codes can be registered to one "License Administrator" or to several different "License Administrators". The License Administrator(s) will be the single point of contact to receive the VMware product serial numbers and all future serial numbers under the VMware Subscription Service.

Each License Administrator is responsible for receiving and administering software product licenses, updates, and upgrades from HP. Upon registration of the activation code(s), you will be prompted to provide the email address of the person(s) you would like listed as the VMware "License Administrator(s)".

Software Subscription Services

You are entitled to Software Subscription Service through your HP Software Technical Support contract included with this license. HP will provide the Software Subscription Service through the activation code registration process. Software Subscription Service will conclude at the end of your Software Technical Support contract with HP. Service must be renewed to continue Software Technical Support and Software Subscription Service.

Technical Support

Your VMware, Insight Control, and SMP licenses include one year of 9x5 HP Software Technical Support and Software Subscription Service. Registration for this service will automatically take place upon redemption of the license certificate/key online. For technical issues using VMware products purchased through HP, use your standard support process to contact the HP support center. For a complete list of HP phone contacts:

http://welcome.hp.com/country/us/en/wwwcontact_us.html

Count on HP for Software Support Solutions

The VMware virtualization software you purchased from HP includes one year of 9x5 unlimited Software Technical Support and Software Subscription Service for ICE. To obtain your software and receive support you must register your support.

To access your software download and register to receive support for the VMware products you have purchased you must register and activate your Software Support Pack at the HP VMware Registration page:

www.hp.com/go/vmwaredownload

The following support upgrade options are available:

- One year of 24 x 7 support
- Three years of 9 x 5 support
- Three years of 24 x 7 support

To upgrade your support or to receive additional information about VMware software support upgrades, contact HP Services at:

http://welcome.hp.com/country/us/en/wwwcontact_us.html

You can order the HP Insight Software media kit for your product directly from HP or your preferred reseller. HP recommends that you download and install the latest product software from the URL listed above.

For support, call 1-800-HP-INVENT (1-800-474-6836). When prompted, say "Insight Manager."

Software is subject to the terms and conditions described in the End User License Agreement (EULA). During installation, be sure to read the EULA carefully before proceeding.



© 2008, 2009 Hewlett Packard Development Company L.P.
VMware is a registered trademark of VMware Inc.
VMware ESX Server, and VMware Virtual SMP are trademarks of VMware Inc.

Fourth Edition (April 2009)
Part Number 480504-024

HP Insight Server Migration software for ProLiant X2V 1 5 1

VMware Insight Control SMP 1
HP VMware

1. HP Insight Server Migration for ProLiant []

HP HP Web http://welcome.hp.com/country/jp/ja/contact_us.html

2. []

HP

HP Web <http://www.hp.com/jp/insightcontrol>

HP VMware 1 ICE

-
-
-

VMware

VMware http://www.hp.com/jp/vmware_code HP Web Partner
Activation Code PAC

• HP HP

[Partner Activation Code Registration] PAC

• 24x 7 3

VMware VMM HP Web http://www.hp.com/jp/carepack_proliant []

HP Insight Software HP URL

1 License Administrator License Administrators

License Administrator VMware

VMware

EULA EULA

License Administrator HP

VMware License

Administrator

HP